

2、 Control PWM servo gimbal

- 2、 Control PWM servo gimbal
 - 2.1 Experimental goals
 - 2.2 Experiment preparation
 - 2.3 Experiment procedure
 - 2.4 Experiment summary

2.1 Experimental goals

This course mainly learns how to control the functions of the robot servo gimbal.

2.2 Experiment preparation

The functions of the Muto hexapod robot Python library involved in this course are as follows:

Gimbal_1_2(S1, S2): To control the servo gimbal, the parameters S1/S2 represent the angle value of the PWM servo S1/S2. The valid value range of S1 is [0, 180], and the valid value range of S2 is [0, 115].

When a certain value in S1/S2 is -1, it means that the PWM servo is not operated. If you only need to control the S1 servo and do not need to change the position of the S2 servo, just pass S2 to -1.

PWM servo gimbal wiring situation:


The lower servo is connected to S1


The upper servo is connected to S2

The black/brown wire plugs into GND

The red wire plugs into 5V

The orange wire plugs into S1/S2





2.3 Experiment procedure

Open the jupyterLab client and find the code path:


```
muto/Samples/Control/2.pwm_servo.ipynb
```

By default `g_ENABLE_CHINESE=False`, if you need to display Chinese, please set `g_ENABLE_CHINESE=True`.

```
# 中文开关, 默认为英文 Chinese switch. The default value is English
g_ENABLE_CHINESE = False

Name_widgets = {
    'End': ("End", "结束")
}
```

Click to run all cells, and then scroll to the bottom to see the generated controls.



You can control different functions by operating different controls separately.

S1	<input type="range"/>	90
S2	<input type="range"/>	20

End

Each time you slide the S1 slider, the angle of the robot's S1 servo will be immediately changed, thereby controlling the left and right rotation of the camera on the servo gimbal. In the same way, every time you slide the S2 slider, the angle of the robot's S2 servo will be immediately changed, thereby controlling the up and down rotation of the camera on the servo platform.

```
def pwm_servo(S1, S2):  
    g_bot.Gimbal_1_2(S1, S2)  
    return S1, S2
```

2.4 Experiment summary

We only need to use the JupyterLab control to control the servo platform of the hexapod robot. By dragging the slider of S1/S2, we can easily adjust the area where the camera on the servo platform collects images.

If you need to exit the program, please press the End button to exit the program. The program will automatically reset the servo gimbal to its initial position.

Note: Although the camera is mentioned in this routine, it does not drive the camera in the program. It is only used as a functional explanation. There will be routines related to the practical application of driving the servo + camera in subsequent courses.